

WinGuard System Requirements

Updated March 2025

The hardware requirements depend on the expansion stage of the system and the integrated subsystems. The following system requirements apply for the standard expansion stages:

	Client/Express	Basic/Interface/ Location Server	Professional Server	Enterprise Server
Operating	Windows 10 Pro	Windows Server	Windows Server	Windows Server
System	(64-Bit)	2016 / 2019 / 2022	2016 / 2019 / 2022	2016 / 2019 / 2022
	Windows 11			
CPU Type	6+ cores	4+ cores	6+ cores	8+ cores
	3,9 GHz+	3,7 GHz+	3,5 GHz+	3,2 GHz+
	Highest CPU GHz recommended. WinGuard will use multiple cores for many tasks.			
Memory	16 GB RAM	8 GB RAM	16GB RAM	32 GB RAM
Storage	100 GB NVMe SSD ¹	250 GB NVMe SSD ¹	500 GB NVMe SSD ¹	1 TB NVMe SSD ¹
	Highest IOPS performance recommended: Maximum IOPS will be beneficial for Database			
	and User Interface performance.			
Graphics Card	4 GB PCIe 2	-	-	-
Network	1 Gbit	1 Gbit	1 Gbit	1 Gbit

¹⁾ The required storage space depends on the system usage and the system settings. For operation of a WinGuard Server, at least 100 GB available **local** disk space is required. A WinGuard workstation requires at least 50GB available **local** disk space. The usage of redundant local disks (e.g. RAID-technology) is recommended for safeguarding against failure.

Notes

Dependencies

WinGuard requires certain dependencies to be installed. These are part of the setup files provided and also available through the integrated Update Manager and the Partner Portal.

Mobile apps and web client

The requirements and limitations of the mobile apps and the web client are described in the respective manuals.

Compatibility

A binding statement about the compatibility of the used operating system in combination with the installed software components of other manufacturers (e.g. required SDKs or APIs) cannot be given by Advancis Software & Services GmbH but only by the respective manufacturers.

Time synchronization

For the operation of WinGuard, the time synchronization between the network participants must be ensured, e.g. via a domain server, an NTP server or a WinGuard function. However, the latter requires starting of WinGuard with administrator rights.

User account control

In order to use WinGuard, especially the "Watch-Dog"-function, write/read permissions of the program directory are required. This may go along with the configuration of the user account control of Windows 10 Pro (or more recent) and Windows Server 2016 (or more recent).

²) When using video integrations please take the system requirements of the VMS vendor into account.



Anti-Virus software

Using Anti-Virus software can cause interferences between the access from WinGuard and access from Anti-Virus software to critical system files. Therefore, access can be blocked or delayed. We suggest taking precautionary measures (e.g. adding the WinGuard files/folders to the exclusion list of the Anti-Virus software).

Operating system patches/updates

Windows operating system patches/updates always need to be up-to-date. It is required that patches/updates recommended by Microsoft are installed.

Software Security and Hardening

Please note the information on system hardening in the WinGuard manual, chapter "Software security". Regarding the use of the WinGuard web server, please note the information in the manual in the "Web server and web client" chapter.

Virtual Machines

WinGuard has been designed to run on dedicated hardware under a Windows operating system. A virtualization of the hardware by hardware emulation/hardware virtualization or para-virtualization is possible subject to the following restrictions:

System restrictions

As WinGuard is, depending on the project, using numerous interface modules to connect the hard- and software of third party manufacturers, it must be ensured that all components linked to the total system are functional in a (partly) virtualized environment.

For serial connections it must be ensured that the connection must be similar to real hardware, e.g. with regard to the timing behaviour for sending/receiving of telegrams.

Advancis Software & Services GmbH cannot give any binding information about the virtualization characteristics of any connected third-party system. Problems might occur especially upon switching the Virtual Machine for load balancing or high availability purposes. To ensure high operation reliability it is recommended to use the proprietary Hot-Standby system of WinGuard instead.

License restrictions

If WinGuard software licenses are applied, please note that the hardware specifications of the used virtual machine must be invariable as otherwise a new activation of the software license will be necessary. The linkage to the system hardware is established based on the Serial number of the system drive and the MAC address of a network adapter.

As it depends on the applied virtualization system which actions lead to a system hardware change of the host system, it is not possible to provide further information about the general possibility to copy/switch the host system between different hosts without a new activation.

If the system hardware of the host system is changed regularly, a hardware dongle should be used to avoid required reactivation efforts.

Additional Information

For additional information please consult the WinGuard Manual, make use of the Partner Portal or contact us directly.